

How to use Auto-Paginated Lists and Grids in iNomads

The *i*Nomads Evolution

How can we improve page load times?



Auto-Paginated Lists and Grids

- Scrollable versus Paged output

Client ID	Name	
016057	Hemphill Theatre	9489 Cozy St
022632	Irion Winery	4490 Middle
024363	Falls Theatre	889 Noble Sp
032475	Brewster Lighting	5998 Dusty C
033994	Jackson Formal Rentals	5201 Lost Jel
034538	Grayson Nursery	1737 Hazy St
038024	Burleson Construction	5574 Bright C
038588	Clay Medical Center	7158 Lazy Cr

Client ID	Name	
016057	Hemphill Theatre	9489 Cozy Shad
022632	Irion Winery	4490 Middle Pla
024363	Falls Theatre	889 Noble Sprin
032475	Brewster Lighting	5998 Dusty Circ
033994	Jackson Formal Rentals	5201 Lost Jetty
034538	Grayson Nursery	1737 Hazy Stead
038024	Burleson Construction	5574 Bright Gre

Pg: 1 2 ... 29

Current Page

Jump to Page

Shift Columns



Auto-Paginated Lists and Grids

- Advantages of Paged output
 - Faster load times for large lists
 - Only sends one page at a time
 - Easier to control on touch screens, such as, a Smartphone
 - Scroll bars can conflict with scrolling of screen
 - User knows roughly the number of items in list/grid
 - Total number of pages defines list length



Auto-Paginated Lists and Grids

- Using Paged list boxes/Grids
 - Controlled by template
 - Check box on the “Lists” tab for template configuration
 - Will apply to ALL lists/grids more than 5 or more lines high
 - Override with *iNomads* class in Nomads definition
 - “**pagedview**” forces paged output
 - “**scrollview**” forces scrollable output
 - No program changes
 - Program does not know output is being paged
 - Continue to load list box / grid as per normal



Additional Resources

The help link(s) below refer to the current on-line help pages. The functionality may have been further updated since the PxPlus 2016 (version 13) release.

- [Template configuration for list views](#)

